

# R'DASH API Reference

**Version:** 1.3

**Protocol:** HTTP / HTTPS

**Author:** Vamsi Karnam

**License:** Apache 2.0

---

## Table of Contents

1. [Overview](#)
  2. [Authentication](#)
  3. [Data Handling](#)
  4. [Core Endpoints](#)
  5. [Video Streaming Endpoint](#)
  6. [WebSocket Stream](#)
  7. [Example Workflow](#)
  8. [Attribution](#)
  9. [Appendix](#)
- 

## Overview

R'DASH exposes a **stateless HTTP + WebSocket API** for live telemetry ingestion, visualization, and management. It accepts push events from **R'DASH Agents** or any compatible client, and serves data, metadata, and MJPEG streams to scripts.

- Base URL example: `http://host-ip:8080` or `https://host-ip:8443`
  - All data is held **in-memory only** (no persistence).
  - All requests require authentication unless the server was started without `--auth-token`.
- 

## Authentication

### Bearer Token

All protected endpoints accept:

Authorization: Bearer <YOUR\_TOKEN>

Example with curl:

```
curl -H "Authorization: Bearer devtestkey" http://host-ip:8080/api/robots
```

### Query-param token (for video endpoints only)

You can alternatively append:

?token=<YOUR\_TOKEN>

Example:

`https://host-ip:8443/video/mybot/camera%2Fimage%2Fcompressed?token=devtestkey`

---

# Data Handling

## Data Model

Concept	Meaning
<b>Robot</b>	Unique name of a connected robot or agent (--robot-name).
<b>Sensor</b>	A topic name, flattened to a URL-safe identifier (slashes encoded as %2F).
<b>Metric key</b>	A flattened field key from the message (e.g., twist.linear.x, data).
<b>t</b>	UNIX timestamp in seconds (float).
<b>data</b>	Map of { field_name: value } for numeric pushes.

## Data Types

Field	Type	Description
robot	text	Robot name
sensor	text	Sensor name (topic path)
type	text	ROS2 type (sensor_msgs/msg/Image or CompressedImage)
image	file	Image binary (image/jpeg, image/png, etc.)
data	data	Numeric value (float32)

## Status Codes

Code	Meaning
200	OK
201	Created (optional)
400	Malformed input
401	Unauthorized (bad/missing token)
404	Robot/sensor not found
413	Payload too large (violates max_image_bytes, etc.)
500	Server error

## Core Endpoints

### 1. POST /api/push

- Push a **numeric sample** (float values).

#### Request (JSON)

```
{  
  "robot": "mybot",  
  "sensor": "drone/speed_mps",  
  "t": 1731010101.234,  
  "data": { "data": 2.22 },  
  "type": "std_msgs/msg/Float32",  
  "units": { "data": "m/s" }  
}
```

#### Curl

```
curl -X POST http://host-ip:8080/api/push -H "Authorization: Bearer devtestkey" \  
-H "Content-Type: application/json" \  
-d  
'{"robot":"mybot","sensor":"drone/speed_mps","t":1731010101.234,"data":{"data":2.22},"type":"st  
d_msgs/msg/Float32","units":{"data":"m/s"}}'
```

#### Python

```
import requests, time  
  
payload = {  
  "robot": "mybot",  
  "sensor": "drone/speed_mps",  
  "t": time.time(),  
  "data": {"data": 2.22},  
  "type": "std_msgs/msg/Float32",  
  "units": {"data": "m/s"}  
}  
  
r = requests.post("http://host-ip:8080/api/push",  
                  headers={"Authorization": "Bearer devtestkey"},  
                  json=payload)  
  
print(r.status_code)
```

#### Response

```
{ "status": "ok" }
```

## 2. POST /api/push\_image

- Push an **image or video frame**.

### Curl

```
curl -X POST http://host-ip:8080/api/push_image \
-H "Authorization: Bearer devtestkey" \
-F "robot=mybot" \
-F "sensor=drone/camera/image/compressed" \
-F "type=sensor_msgs/msg/CompressedImage" \
-F "image=@frame.jpg;type=image/jpeg"
```

### Python

```
import requests

with open("frame.jpg", "rb") as f:

    files = {"image": ("frame.jpg", f, "image/jpeg")}

    data = {

        "robot": "mybot",

        "sensor": "drone/camera/image/compressed",

        "type": "sensor_msgs/msg/CompressedImage"

    }

    r = requests.post("http://host-ip:8080/api/push_image",
                      headers={"Authorization": "Bearer devtestkey"},
                      files=files, data=data)

print(r.json())
```

### Response

```
{ "status": "ok", "bytes": 84231 }
```

### 3. POST /api/push\_tf

- Push **TF edges** (parent → child links).

#### Request

```
{  
  "robot": "mybot",  
  "edges": [["base_link","camera_link"],["base_link","lidar_link"]]  
}
```

#### Curl

```
curl -X POST http://host-ip:8080/api/push_tf \  
-H "Authorization: Bearer devtestkey" \  
-H "Content-Type: application/json" \  
-d '{"robot":"mybot","edges": [["base_link","camera_link"],["base_link","lidar_link"]]}'
```

#### Response

```
{ "status": "ok", "count": 2 }
```

---

### 4. POST /api/push\_text

- Push a **log / textual line**.

#### Request

```
{  
  "robot": "mybot",  
  "sensor": "drone/log",  
  "t": 1731010105.0,  
  "text": "[DRONE] armed=1 mode=GUIDED"  
}
```

#### Curl

```
curl -X POST http://host-ip:8080/api/push_text \  
-H "Authorization: Bearer devtestkey" \  
-H "Content-Type: application/json" \  
-d '{"robot":"mybot","sensor":"drone/log","t":1731010105.0,"text":"[DRONE] armed=1  
mode=GUIDED"}'
```

## Python

```
import requests, time  
  
payload = {  
    "robot": "mybot",  
    "sensor": "drone/log",  
    "t": time.time(),  
    "text": "[DRONE] altitude=5.1m speed=2.2m/s"  
}  
  
requests.post("http://host-ip:8080/api/push_text",  
    headers={"Authorization": "Bearer devtestkey"},  
    json=payload)
```

---

## 5. POST /api/push\_file

Push an arbitrary file artifact (logs, audio clips, JSON dumps, etc.) and persist it on disk.

### Files are stored under:

*files/<robot>/<sensor-path>*

and automatically appear in the Files drawer for that robot in the web UI.

The sensor path must include a “file” segment (case-insensitive).

This is used to route the artifact into the Files side panel.

### Request Method: POST

Content-Type: multipart/form-data

Size limit: governed by RDASH\_MAX\_UPLOAD\_BYTES (default ~200 MB per request).

Oversized uploads return 413 Payload Too Large.

### Example sensor paths

*file/debug/session\_001.log*

*my\_robot\_01/file/dumps/heap\_snapshot.bin*

*file/audio/debug\_clip.flac*

**These show up in the Files drawer as accordion topics:**

*file*  
*file/debug*  
*file/dumps*

Each accordion lists the stored filenames as clickable download links.

## Curl

```
curl -X POST http://host-ip:8080/api/push_file \
-H "Authorization: Bearer devtestkey" \
-F "robot=my_robot_01" \
-F "sensor=file/my_file.flac" \
-F "file=@my_file.flac"
```

## Python

```
import requests
token = "devtestkey"
base = "http://host-ip:8080"
robot = "my_robot_01"
sensor = "file/my_file.flac"
with open("my_file.flac", "rb") as f:
    files = {"file": ("my_file.flac", f)}
    data = {
        "robot": robot,
        "sensor": sensor,
    }
r = requests.post(
    f"{base}/api/push_file",
    headers={"Authorization": f"Bearer {token}"},
    files=files,
    data=data,
)
print(r.status_code, r.json())
```

On success:

```
{ "ok": true, "robot": "my_robot_01", "sensor": "file/my_file.flac" }
```

---

## 6. GET /api/robots

- List all active robots and their sensors.

### Curl

```
curl -s http://host-ip:8080/api/robots -H "Authorization: Bearer devtestkey" | jq
```

### Response

```
{
  "robots": [
    {
      "name": "mybot",
      "sensors": ["drone/speed_mps", "drone/altitude_m", "drone/log"],
      "last_seen": 1731010111.22
    }
  ]
}
```

---

## 7. GET /api/meta/<robot>/<sensor>

- Retrieve metadata for a given sensor.

### Curl

```
curl http://host-ip:8080/api/meta/mybot/drone%2Fspeed_mps \
-H "Authorization: Bearer devtestkey"
```

### Response

```
{
  "type": "std_msgs/msg/Float32",
  "units": { "data": "m/s" },
  "last": 1731010110.232,
  "status": "active"
}
```

---

## 8. GET /api/history/<robot>/<sensor>

- Return recent numeric samples (from RAM ring buffer).

### Curl

```
curl http://host-ip:8080/api/history/mybot/drone%2Fspeed_mps \
-H "Authorization: Bearer devtestkey"
```

### Response

```
{
  "t": [1731010098.1, 1731010098.2, 1731010098.3],
  "data": { "data": [2.15, 2.20, 2.22] }
}
```

---

## 9. GET /api/text\_history/<robot>/<sensor>

- Return the recent text log lines for that sensor.

### Response

```
{
  "lines": [
    {"t":1731010101.0, "text":"[DRONE] armed=1"},
    {"t":1731010102.0, "text":"[DRONE] altitude=5.2"}
  ]
}
```

---

## 10. POST /api/delete\_series/<robot>/<sensor>

- Clear numeric series (RAM reset).

```
curl -X POST http://host-ip:8080/api/delete_series/mybot/drone%2Fspeed_mps \
-H "Authorization: Bearer devtestkey"
```

---

## **11. POST /api/delete\_text/<robot>/<sensor>**

- Clear text/log history (RAM reset).

```
curl -X POST http://host-ip:8080/api/delete_text/mybot/drone%2Flog \  
-H "Authorization: Bearer devtestkey"
```

---

## Video Streaming Endpoint

### **1. GET /video/<robot>/<sensor>**

- Returns an **MJPEG multipart stream** suitable for embedding in a browser or HTML <img> tag.

#### **Example (browser)**

http://host-  
ip:8080/video/mybot/drone%2Fcamera%2Fimage%2Fcompressed?token=devtestkey

#### **Curl**

```
curl -H "Authorization: Bearer devtestkey" \ http://host-  
ip:8080/video/mybot/drone%2Fcamera%2Fimage%2Fcompressed --output stream.mjpeg
```

---

## WebSocket Stream

**URL:** /ws

**Protocol:** wss://HOST/ws or ws://HOST/ws

- Authenticated via Bearer token in headers (handled automatically by browser).
- Emits coalesced JSON updates for all active sensors at RDASH\_WS\_FLUSH\_HZ (default 20 Hz).

#### **Sample event payload**

```
{  
  "robot": "mybot",  
  "sensor": "drone/speed_mps",  
  "t": 1731010102.25,  
  "data": { "data": 2.23 }  
}
```

---

## Example Workflow (End-to-End)

### 1. Push a numeric sample

```
curl -X POST $BASE/api/push "${HDR[@]}" -d
'{"robot":"demo","sensor":"power/battery_mv","t":1731010100,"data":{"data":25000},"type":"std_msgs/msg/Float32","units":{"data":"mV"}'
```

### 2. Fetch history

```
curl $BASE/api/history/demo/power%2Fbattery_mv "${HDR[@]}"
```

### 3. Push a text log line

```
curl -X POST $BASE/api/push_text "${HDR[@]}" -d
'{"robot":"demo","sensor":"robot/log","t":1731010110,"text":"Battery 25.0mV"}'
```

### 4. View MJPEG feed

Open:

```
http://host-
ip:8080/video/demo/drone%2Fcamera%2Fimage%2Fcompressed?token=devtestkey
```

### 5. Inspect metadata

```
curl $BASE/api/meta/demo/power%2Fbattery_mv "${HDR[@]}"
```

### 6. Push a file via API

```
curl -X POST http://host-ip:8080/api/push_file -H "Authorization: Bearer devtestkey" -F
"robot=my_robot_01" -F "sensor=file/my_file.flac" -F "file=@my_file.flac"
```

---

## Notes

- All times are **UNIX float seconds (UTC)**.
- JSON keys are **case-sensitive**.
- Images larger than rdash\_MAX\_IMAGE\_BYTES are rejected.
- Text history and numeric samples are **per-sensor ring buffers** trimmed to rdash\_MAX\_SAMPLES.
- Restarting the server wipes all state.

---

## Attribution

R'DASH - Robot Information Telemetry Transport Dashboard

Developed by **Vamsi Karnam**, 2025.

Apache License 2.0

---

## Appendix

### I. DDS Topics

Rdash\_v1.1 introduces support for DDS-originated telemetry by design.

Any topic whose path includes the segment **dds** (case-insensitive) is automatically routed to the **DDS side panel** in the web dashboard, keeping infrastructure and diagnostic data separate from regular robot sensors.

This feature is entirely **agnostic** - it does not introduce a new data type or API endpoint.

DDS data continues to flow through the same core interfaces:

DDS Data Type	API Endpoint	Visualization
Numeric DDS metric	/api/push	Displayed under <b>DDS → Metrics</b>
Textual DDS log	/api/push_text	Displayed under <b>DDS → Logs</b>
(Optional) DDS media data	/api/push_image	Accepted but <b>not visualized</b>

#### Behavior

- The presence of “dds” in a topic’s path determines whether it appears in the DDS drawer.
- DDS filtering is purely **semantic** - it changes presentation, not storage or transport.
- Numeric and text topics under dds namespaces behave identically to their non-DDS counterparts, but are grouped separately in the UI.

#### DDS Topic Guidelines

The DDS panel is designed for **numeric** and **textual** system telemetry such as diagnostics, CPU usage, latency, and network metrics.

While R'DASH will technically accept sensor\_msgs/Image or sensor\_msgs/CompressedImage topics under a dds namespace, such data will **not be visualized** as live camera feeds.

To ensure correct behavior:

- Use the dds namespace for diagnostics and performance data.
- Keep camera, LiDAR, or other media topics outside the DDS path.

#### Examples:

Topic\_1: [/foo/dds/network/latency\\_ms](/foo/dds/network/latency_ms)

Topic\_2: </bar/dds/system/diagnostics>